

# The Modal Shop

## Product Release Note



3149 East Kemper Rd.  
Cincinnati, OH 45241  
Ph : 513-351-9919  
Fax: 513-458-2172  
www.modalshop.com

**Product Name:** 440 Series Control Software  
**Version:** 2.7.0  
**Release Date:** January 20, 2009

### Compatibility:

1. Operating System: Windows XP, Windows Vista

### Version 2.7.0:

#### Enhancements:

1. TEDS enabled sensors programmed with IEEE1451.4 (version 1.0) templates are now supported by the software. This is in addition to the IEEE P1451.4 (version 0.9) support that previously existed.

#### Upgrades:

1. (Bug Fix) Performing a global channel status will no longer cause the software to crash.
2. (Bug Fix) When closing the software where a bankswitch is present in the 440 rack will no longer occasionally cause a crash response.
3. (Bug Fix) When recalling a configuration file, pressing the "Cancel" button will no longer cause the software to crash.
4. The TEDS Manufacturer list has been updated as of 1/13/2009.

#### Known Issues:

1. Some communication errors have been found to be at fault of USB to RS232 adaptors. TMS recommends using a computer with an RS232 port. If one must be added, attempt to use an expansion card (PCI, PCMCIA, ExpressCard, etc. depending on your computer's capabilities) before a USB adaptor if available. When communication issues occur, one may be required to reboot the 440 series racks.
2. Racks with fewer than eight slots will still appear to have eight slots on the main window.

® ICP is a registered trademark of PCB Group Inc. All other trademarks are property of their respective owners.